

Topic 13: How to Customize Tool Crib


13.0 How to Customize Tool Crib

Steps to customize your tool crib

1. Open a Solidworks part file
2. Click Tools.
3. On the pulldown menu, Click SOLIDWORKS CAM
4. Click Technology Database
5. Follow the steps below to customize your tool crib

- Create a new tool crib


Select **Metric**, click on the **Mill Tab**, then click on **Tool Crib 1(Metric) Empty** under Tool Crib



Module: Solidworks CAM Standard-Milling


Topic 13: How to Customize Tool Crib

Click on **New**, key in the **name of tool crib** and the **number of total stations**, then click on **Save**



- Select the tools from the tool library


Ensure the select tool crib is correct, click on **Add** and select the **tool type**




Module: Solidworks CAM Standard-Milling

Topic 13: How to Customize Tool Crib

Choose the desired diameter, you can make change of tool data if you want. Then click **SELECT**.



Same for other type of tools



Module: Solidworks CAM Standard-Milling

Topic 13: How to Customize Tool Crib

Please specify the Station number for every tool selected and click SAVE

